





1

Go to <https://www.usa.canon.com/support/p/imagerunner-advance-dx-c5870i>

Scroll down the page to the “Downloads” section and download the “UFRii” driver:

File Name Generic_Plus_PCL6_v3.20.zip	Type Drivers	Date 04.23.25	File Size 67.9 MB	DOWNLOAD 
<u>Details</u> ▼				
File Name Generic_Plus_PS3_v3.20.zip	Type Drivers	Date 04.23.25	File Size 63.1 MB	DOWNLOAD 
<u>Details</u> ▼				
File Name Generic_Plus_UFRii_v3.20.zip	Type Drivers	Date 04.23.25	File Size 71.5 MB	DOWNLOAD 
<u>Details</u> ▼				
File Name Generic_Fax_v10.66.zip	Type Drivers	Date 04.17.25	File Size 33.1 MB	DOWNLOAD 
<u>Details</u> ▼				

This one




2

Then go to your Downloads folder, right-click on the file and extract its contents.

3

Go to your computer's
"Printers and Scanners"
settings:



← Settings

Proot

Local Account

Find a setting

System

Bluetooth & devices

Network & internet

Personalization

Apps

Accounts

Time & language

Gaming

Accessibility

Privacy & security

Windows Update

Bluetooth & devices > Printers & scanners

Add a printer or scanner

Add device

copier-100

>

copier-100-through-printserver

>

Microsoft Print to PDF

>

OneNote (Desktop)

>

Printer preferences

Let Windows manage my default printer

On

Download drivers and device software over metered connections

Off

Data charges may apply

Related settings

Print server properties

Troubleshoot

Related support

Click "Add Device"

A large red arrow pointing from the right towards the 'Add device' button in the Windows Settings window.

4

5

Settings

Proot
Local Account

Find a setting

System

Bluetooth & devices

Network & internet

Personalization

Apps

Accounts

Time & language

Gaming

Accessibility

Privacy & security

Windows Update

Bluetooth & devices > Printers & scanners

Add a printer or scanner

Refresh

The printer that I want isn't listed

Add manually

copier-100

copier-100-through-printserver

Microsoft Print to PDF

OneNote (Desktop)

Printer preferences

Let Windows manage my default printer

On

Download drivers and device software over metered connections
Data charges may apply

Off

Related settings

Print server properties


Troubleshoot

Click "Add manually"
(This might not appear
for a few seconds.)

6

Choose this



←  Add Printer

Find a printer by other options

☐ My printer is a little older. Help me find it.

☐ Select a shared printer by name

Browse...

Example: \\computername\printername or
http://computername/printers/printername/.printer

☒ Add a printer using an IP address or hostname

☐ Add a Bluetooth, wireless or network discoverable printer

☐ Add a local printer or network printer with manual settings

Next Cancel

7

Choose "TCP/IP Device"

Enter this address

← Add Printer

Type a printer hostname or IP address

Device type: TCP/IP Device


Hostname or IP address: copier-100.phys.virginia.edu

Port name: copier-100.phys.virginia.edu_1

☒ Query the printer and automatically select the driver to use


Autodetect detects WSD and TCP/IP printers.
To search for an IPP printer, IPP must be selected from the drop down menu.

Next Cancel



Click "Have Disk"

9




Browse through the files you downloaded and extracted earlier. Find the .INF file inside the “x64” folder.

10

Name the printer “copier-100” and accept the defaults for any further settings.

At this point, the printer should be ready to use.



Confirm Department ID/PIN

Confirm Department ID and PIN.

Department ID:

PIN:

OK Cancel Help

When you print, you'll see this dialog box.

Enter your "copy code" in the "Department ID" box.

Leave the "PIN" box empty.