Phys 531 Lecture 14 Fourier Transform

Last time, looked at how waves add Spatial variations: interference pattern Time variations: beat note

Claimed that you could construct arbitrary pulse by adding fields with different  $\omega$ 's

Today, show how: Fourier transform

1

Outline:

- Motivation
- Definition
- Transform properties
- Spatial transforms

Lots of math today

Next time:

- Apply Fourier methods to wave propagation
- Start working on diffraction

## Motivation

```
Lecture 1:

Claimed any wave = sum of plane waves

For now, show that:

Any function of time f(t)

= sum of harmonic functions e^{-i\omega t}

More general: any function

More specific: single variable

imagine f(t) = E(\mathbf{r}, t) at fixed \mathbf{r}


Talk about full waves again at end
```

```
3
```


```
Why should f(t) = \text{sum of } e^{i\omega t}'s?
= sum of sines and cosines?
```

Make components add constructively where f large destructively where f small

Example: add  $f_n = \cos[(1.2)^n \omega t]$  for n = 1 to 9:



Sum gives peak at t = 0:



More cosines  $\rightarrow$  sharper peak, flatter background

If you can make sharp peaks: any f(t) =sum of peaks at different t's

Fourier Transform (Hecht 7.3, 7.4, 11.1) Most general sum = integral Can write  $f(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} F(\omega) e^{-i\omega t} d\omega$ 

 $F(\omega) = \text{coefficients of sum}$  $1/2\pi = \text{normalizing factor}$ 

Fine, but how to determine  $F(\omega)$ ?

Basic Fourier trick:

multiply both sides by  $e^{i\beta t}$  and integrate over t

$$\int_{-\infty}^{\infty} e^{i\beta t} f(t) dt = \frac{1}{2\pi} \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} e^{i\beta t} F(\omega) e^{-i\omega t} d\omega dt$$

Change order of integrals on rhs:

$$= \frac{1}{2\pi} \int_{-\infty}^{\infty} F(\omega) \left( \int_{-\infty}^{\infty} e^{i(\beta - \omega)t} dt \right) d\omega$$
$$= \int_{-\infty}^{\infty} F(\omega) \delta(\beta - \omega) d\omega$$

for

$$\delta(\omega) = \frac{1}{2\pi} \int_{-\infty}^{\infty} e^{i\omega t} dt \equiv$$
 "delta function"

Consider $\delta(\omega)$ (Hecht 11.2.3)
If $\omega \neq 0$ , then $e^{i\omega t}$ oscillates +/-
So $\int e^{i\omega t} dt$ averages to zero:
Expect $\delta(\omega) = 0$ for $\omega \neq 0$

But for 
$$\omega = 0$$
,  $e^{i\omega t} = e^0 = 1$   
So  $\int_{-\infty}^{\infty} e^{i\omega t} dt \rightarrow \int_{-\infty}^{\infty} dt = \infty$ 

Like adding up infinite number of cosines: get infinitely high, infinitely narrow peak

Important property:

$$\int_{-\infty}^{\infty} \delta(\omega) d\omega = \frac{1}{2\pi} \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} e^{i\omega t} dt \, d\omega = 1$$

delta function is normalized

Derived in handout

Go back to

$$\int_{-\infty}^{\infty} e^{i\beta t} f(t) dt = \int_{-\infty}^{\infty} F(\omega) \delta(\beta - \omega) d\omega$$

delta function peaked at  $\omega=\beta$ , zero elsewhere

At 
$$\omega = \beta$$
, have  $F(\omega) = F(\beta)$ 

So have

$$\int_{-\infty}^{\infty} e^{i\beta t} f(t) dt = F(\beta) \int_{-\infty}^{\infty} \delta(\beta - \omega) d\omega = F(\beta)$$

Usually write

$$F(\omega) = \int_{-\infty}^{\infty} f(t)e^{i\omega t}dt$$

Call F = Fourier transform of f

Then f = inverse Fourier transform of F:

$$f(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} F(\omega) e^{-i\omega t} d\omega$$

Other definitions possible:

$$F(\omega) = \frac{1}{\sqrt{2\pi}} \int_{-\infty}^{\infty} f(t) e^{-i\omega t} dt$$
$$f(t) = \frac{1}{\sqrt{2\pi}} \int_{-\infty}^{\infty} F(\omega) e^{i\omega t} d\omega$$
or  $F(\nu) = \int_{-\infty}^{\infty} f(t) e^{i2\pi\nu t} dt$ 

$$f(t) = \int_{-\infty}^{\infty} F(\nu) e^{-i2\pi\nu t} d\nu$$


 $\nu=\omega/2\pi$  = frequency in Hz

Our version: all  $\omega$  integrals have  $1/2\pi$  factor

11

Do an example:


Say 
$$f(t) = 1/\tau$$
 if  $-\frac{\tau}{2} < t < \frac{\tau}{2}$   
= 0 otherwise



Normalized to 1

Calculate  $F(\omega)$ :

$$F(\omega) = \int_{-\infty}^{\infty} f(t)e^{i\omega t}dt$$
$$= \frac{1}{\tau} \int_{-\tau/2}^{\tau/2} e^{i\omega t}dt$$
$$= \frac{1}{i\omega\tau} \left( e^{i\frac{\omega\tau}{2}} - e^{-i\frac{\omega\tau}{2}} \right)$$
$$= \frac{2}{\omega\tau} \sin\left(\frac{\omega\tau}{2}\right)$$



Define  $\sin(\theta)/\theta \equiv \operatorname{sinc} \theta$ 

Have sinc(0) = 1 (peak value)

$$sinc(n\pi) = 0$$
 (integer  $n \neq 0$ )

Peak width  $\Delta \theta \approx 2\pi$ 

So  $F(\omega) = \operatorname{sinc}\left(\frac{\omega\tau}{2}\right)$ Peaked at  $\omega = 0$ Width  $\Delta \omega = \pi/\tau$ 

General feature: width  $\Delta \omega$  of  $F(\omega)$  larger when width  $\Delta t$  of f(t) is smaller

Can show  $\Delta \omega \Delta t \ge 1/2$ (for particular definition of widths)

15

Need high frequencies if f changes quickly always expect  $\omega_{\max} \approx 1/\delta t$  $\delta t$  = time scale for f(t) to change

For rectangular pulse,  $\delta t \rightarrow 0$ 

See  $F(\omega)$  decreases slowly  $\propto \omega^{-1}$  for  $\omega \to \infty$ no definite  $\omega_{max}$ 

**Question:** If we set  $F(\omega) = 0$  for  $|\omega|$  greater than some  $\omega_{\text{max}}$ , how would f(t) change?

Properties of Fourier Transform (Hecht 11.2, handout)

A. Even for real f(t),  $F(\omega)$  can be complex

$$F(\omega) = \int f(t)e^{i\omega t}dt$$
$$F^*(\omega) = \int f(t)e^{-i\omega t}dt$$

So 
$$F - F^* = \int f(t) \left( e^{i\omega t} - e^{-i\omega t} \right) dt$$
  
=  $2i \int f(t) \sin(\omega t) dt$   
= 0 only if  $f(t) = f(-t)$ 

Why is F complex? Because we defined F with complex exponentials

Also explains why we get  $\omega < 0$  terms: in complex space  $\omega < 0$  and  $\omega > 0$  are different If f real, then  $F(-\omega) = F^*(\omega)$ all information in  $\omega > 0$  terms

Fits well with complex representation of fields: we're just suppressing  $\omega < 0$  components

B. Linearity

If  $f(t) = af_1(t) + bf_2(t)$  then  $F(\omega) = aF_1(\omega) + bF_2(\omega)$ where  $F_1$  = transform of  $f_1$  $F_2$  = transform of  $f_2$ 

Very useful: Often complicated f = sum of simple f's


Example: = + +Say pulses width *T*, height = *A* Gap width = *T* Remember sinc( $\omega \tau/2$ ) = transform of pulse width  $\tau$ , height  $1/\tau$ First pulse width  $\tau = 3T$ , second pulse  $\tau = T$ Adjust amplitudes of *F* accordingly Then  $F(\omega) = 3AT \operatorname{sinc}\left(\frac{3\omega T}{2}\right) - AT \operatorname{sinc}\left(\frac{\omega T}{2}\right)$ 

If  $f(t) = g(t + \tau)$  then  $F(\omega) = e^{-i\omega\tau}G(\omega)$ where G = transform of g

If  $f(t) = e^{-i\omega_0 t}g(t)$  then  $F(\omega) = G(\omega - \omega_0)$ 

Also useful for obtaining new transforms

21



Peak in  $\omega$  space centered at  $\omega_0$ 

**Question:** What would the transform look like if  $f = \cos(\omega_0 t)$  for  $|t| < \tau/2$  and f = 0 otherwise?

## D. Convolution

If  $F(\omega) = F_1(\omega)F_2(\omega)$ , then  $f(t) = \int_{-\infty}^{\infty} f_1(T)f_2(t-T)dT$ where  $f_1, f_2$  = inverse transforms of  $F_1, F_2$ Say that f = convolution of  $f_1$  and  $f_2$ Lets you modify  $F(\omega)$  and understand result

Example:  $f_1(t) = 1/\tau$  if  $(|t| < \tau/2)$ Then  $F_1(\omega) = \operatorname{sinc}(\omega\tau/2)$ 

23

Multiply  $F_1$  by  $F_2$   $F_2(\omega) = 1$  if  $|\omega| < \omega_{max}$  $F_2(\omega) = 0$  otherwise

Chops off high frequencies, as before

What is  $f_2(t)$ ?

$$f_{2}(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} F_{2}(\omega) e^{-i\omega t} d\omega$$
$$= \frac{1}{2\pi} \int_{-\omega_{m}}^{\omega_{m}} e^{-i\omega t} d\omega$$
$$= \frac{1}{\pi t} \sin(\omega_{m} t) = \frac{\omega_{m}}{\pi} \operatorname{sinc} \omega_{m} t$$


(Form of f and F interchangable)

So we get

$$f(t) = \int_{-\infty}^{\infty} f_1(T) f_2(t-T) dT$$

If  $\omega_m$  is large then  $f_2$  is sharp peak - only large for  $|\omega_m(t-T)| < \pi$ So need T pretty close to t:  $f(t) \approx f_1(t)$ 

But edges of pulse "blurred" like sinc



E. Correlation

Suppose  $f(t) = \int_{-\infty}^{\infty} f_1^*(T) f_2(t+T) dT$ Say f = correlation of  $f_1$  and  $f_2$ Fancy way to compare two functions - we'll use later

Obtain  $F(\omega) = F_1^*(\omega)F_2(\omega)$ 

Similar to convolution result

27

F. Parseval's Theorem


If  $F(\omega)$  is transform of f(t) then

$$\int_{-\infty}^{\infty} |f(t)|^2 dt = \frac{1}{2\pi} \int_{-\infty}^{\infty} |F(\omega)|^2 d\omega$$

For wave,  $\int |f(t)|^2 dt \propto \text{total energy in wave}$ Interpret  $|F(\omega)|^2 d\omega \propto \text{energy in frequency band } d\omega$ 

Can measure: Send light pulse through dispersing prism separates colors =  $\omega$  components Intensity of each color  $\propto |F(\omega)|^2$ 

## List of transforms



Use with linearity and scaling properties: gives most of what we need

## Spatial transforms

If f(z) is function of spatial coordinate

$$f(z) = \frac{1}{2\pi} \int_{-\infty}^{\infty} F(k) e^{ikz} dk$$
$$F(k) = \int_{-\infty}^{\infty} f(z) e^{-ikz} dz$$

So (z,k) like  $(t,\omega)$ : everything works the same

**Question:** My definition of  $F(\omega)$  had  $e^{i\omega t}$ . Why did I change the sign for F(k)?

For 3D functions, need 3D transform:

$$f(\mathbf{r}) = \frac{1}{(2\pi)^3} \iiint F(\mathbf{k}) e^{i\mathbf{k}\cdot\mathbf{r}} d^3k$$

$$F(\mathbf{k}) = \iiint f(\mathbf{r})e^{-i\mathbf{k}\cdot\mathbf{r}}d^3r$$

integrals over all space

Same ideas, sometimes integrals are harder We'll see one example later

For instance:  $|F(\mathbf{k})|^2$  = energy density at wave vector  $\mathbf{k}$ 

31

What about space and time together?

Write

$$f(\mathbf{r},t) = \frac{1}{(2\pi)^4} \int F(\mathbf{k},\omega) e^{i(\mathbf{k}\cdot\mathbf{r}-\omega t)} d^3k \, d\omega$$

$$F(\mathbf{k},\omega) = \int f(\mathbf{r},t)e^{-i(\mathbf{k}\cdot\mathbf{r}-\omega t)}d^{3}r\,dt$$

Works for any function f

Can write any function as sum of plane waves! as advertised in Lecture 1 What about waves?

Say electric field  $E(\mathbf{r},t)$ 

Write transform as  $\mathcal{E}(\mathbf{k},\omega)$ 

$$E(\mathbf{r},t) = \frac{1}{(2\pi)^4} \int \mathcal{E}(\mathbf{k},\omega) e^{i(\mathbf{k}\cdot\mathbf{r}-\omega t)} d^3k \, d\omega$$

But, if E is solution of wave equation, need

$$k^2 = \frac{n^2 \omega^2}{c^2}$$

Not all functions are waves

33

Then  $\omega$  and  ${\bf k}$  aren't independent

Really only three variables: use  $\mathbf{k}$ 

then  $\omega = \omega(\mathbf{k}) \equiv \omega_k$ 

Then if

$$\mathcal{E}(\mathbf{k}) = \int E(\mathbf{r}, 0) e^{-i\mathbf{k}\cdot\mathbf{r}} d^3r$$

get 
$$E(\mathbf{r},t) = \frac{1}{(2\pi)^3} \int \mathcal{E}(\mathbf{k}) e^{i(\mathbf{k}\cdot\mathbf{r}-\omega_k t)} d^3k$$

Gives wave at all times in terms of  $E(\mathbf{r}, t = 0)$ 

**Question:** What if E(t = 0) is zero everywhere, and at some later time I turn on a source?

Summary:

- Fourier transform lets you express functions as sum of harmonic functions
- Evaluate transform by doing integral
- Covered several important properties
- Can do transforms in space and/or time
- For waves, space and time dependence related